

Network V5 license installation and activation


Caution:

1/ The activation of the network license must only be done once! All workstations that then want to use the license should refer to the procedure: [Connexion to a network license](#)

2/ To activate the license it is necessary to have **MODIFY** rights on the **UNC license directory**

1/ Installation of Phase Manager

Run the setup and choose the installation language:



Skip the welcome screen by clicking on **Next** :



Accept the license agreement then click on **Next** :

License Agreement

Please read the following important information before continuing.

Please read the following License Agreement. You must accept the terms of this agreement before continuing with the installation.

LICENCE D'UTILISATION
DU LOGICIEL PHASE MANAGER

Article 1 - Objet des présentes conditions générales
Les présentes conditions générales ont pour objet de préciser les conditions dans lesquelles l'EDITEUR PROJET LINEAIRE DEVELOPPEMENT concède à l'UTILISATEUR un droit d'utilisation du LOGICIEL PHASE MANAGER et assure la maintenance dudit LOGICIEL PHASE MANAGER.

Article 2 - Utilisation du LOGICIEL PHASE MANAGER
Le LOGICIEL PHASE MANAGER s'adresse à des utilisateurs confirmés ou non, travaillant sur un environnement Windows uniquement (Vista ou supérieur).

☒ I accept the agreement
☐ I do not accept the agreement

< Back Next > Cancel

Destination location : we **recommend you keep the default path**:



Choose '**Single user installation**'


Select Components

Which components should be installed?


Select the components you want to install; clear the components you do not want to install. Click Next when you are ready to continue.

Single user installation

Validate the Start Menu Folder screen by clicking on **Next** :




Choose and validate the icons creation screen by clicking **Next** :



On the following screen click on **Install** then once installation is complete, click on **Finish**

2/ Network license configuration

Once Phase Manager V5 is installed, double-click on its icon to launch it.
At first launch, the license configurator will display:



To activate your license, you will need to fill in the following fields:

Module

Choose **Réseau**:

Module	Réseau ▼
--------	-----------------

Product ID

Fill in the Product ID that's been sent to you by Projet Linéaire:

- licence pattern : LPMP-00**NNN**0500abcDEF (**NNN** is your license number, and **5** the version)
- **only paste the right part of your Product-ID, after the '-' :**

Module	Réseau ▼
Product ID	LPMP 00NNN0400abcDEF

Activation key

Fill in the Serial number sent to you by Projet Linéaire.

- pattern : VccQX-37eJG-AZIce-EYk7O-temCP-8DRFu

Module	Reseau ▼	
Product ID	LPMP	00NNN0400abcDEF
Activation...	VccQX-37eJG-AZIce-EYk7O-temCP-8DRFu	

Licence

Choisir “*Create new licence*” : ☒ Create new licence ☐ Choose a licence

By clicking on the button you can choose the location of the license file that will be created by Phase Manager:

Indicate a UNC path using the following pattern : **\\SERVER_NAME\SHARE\FOLDER** :


Module	Reseau ▼	
Product ID	LPMP	00NNN0400abcDEF
Activation...	VccQX-37eJG-AZIce-EYk7O-temCP-8DRFu	
Create new licence	☒ Choose a licence ☐	
Browse	\\PI-sv\Share\Shared-License	

3/ License activation

Click now on the button to activate your licence.

Beware : an Internet connection is mandatory to activate the license !

To activate the license, switch to English then choose the option below and click on **Next** :



Activation of PhaseManager

Welcome to PhaseManager

☒ **I have a Serial Number and I want to activate PhaseManager**

Enter the Serial Number to activate PhaseManager.

To get a valid Serial Number, you have to buy the product. You can activate it any time.

If you don't have a Serial Number, you can continue with the evaluation version.

☐ **I want to evaluate PhaseManager (there are 14 day(s) left to evaluate)**

You can evaluate PhaseManager for another 14 day(s). After that you have to activate PhaseManager to further use the product.

English

Next End

- Fill-in all required data then click on Next:
- **The Serial number is the Activation Key that's been used at step 2 in the license configurator**

Activation of PhaseManager

Please enter the activation data

Please enter all required information for the activation process.

Enter Serial Number

JBc F8

[Where do you find your Serial Number?](#)

Enter Name / Company / Organisation

SSA/PL

Enter your E-mail Address


ssauteur@projetlineaire.com

required


English

Back Next End

- Check that you ARE connected to INTERNET then click on Next:



- If the following message is displayed, that means that Phase Manager did activate right. Click on Next to run Phase Manager:



- If you need to, feel free to contact our customer support at support@projetlineaire.com